

PRACTICAL MANUAL

ON

Agrometeorology and Climate Change

HNR 322 2(1+1)

(For Undergraduate Horticulture students)

Dr. Gunjan Guleria



2020

**College of Agriculture
RANI LAKSHMI BAI CENTRAL AGRICULTURAL
UNIVERSITY, Jhansi-284003**

Agro-meteorology and Climate Change HNR 322 2(1+1)

Site selection for Agromet observatory; Measurement of temperature; Measurement of rainfall; Measurement of evaporation (atmospheric/soil); Measurement of atmospheric pressure; Measurement of sunshine duration and solar radiation; Measurement of wind direction and speed and relative humidity; Study of weather forecasting and synoptic charts. Visit to Meteorological observatory, Visit to IMD meteorological observatory-Lay out plan of standard meteorological observatory. Recording of air and soil temperature. Measurement of radiation and components, Measurement of rainfall-different types of rain gauges, Measurement of wind speed and direction and atmospheric humidity, Recording of evaporation. Synoptic charts and weather reports, symbols, etc.

Name of Student

Roll No.

Batch

Session

Semester

Course Name :

Course No. :

Credit

Published: 2020

No. of copies:

Price: Rs.

CERTIFICATE

This is to certify that Shri./Km. ID No.....has completed the practical of course.....course No. as per the syllabus of B.Sc. (Hons.) Agriculture/ Horticulture/ Forestry semester in the year.....in the respective lab/field of College.

Date:

Course Teacher

INDEX

S. No.	Practical Exercise	Page No.
1.	To select the suitable site for the observatory	
2.	To study about layout plan of agrometeorological observatory	
3.	Visit of agro meteorological observatory	
4.	Visit of IMD meteorological observatory	
5.	To measure the maximum and minimum air temperatures	
6.	To measure the soil temperature	
7.	To measure the rainfall	
8.	To tabulate and analyse rainfall	
9.	To measure evaporation	
10.	To measure evapotranspiration	
11.	To study atmospheric pressure	
12.	Measurement of sunshine duration	
13.	Measurement of total radiation	
14.	Measurement of components of solar radiation	
15.	Measurement of wind speed and wind direction	
16.	To study about the wind rose	
17.	To determine the relative humidity and vapour pressure	
18.	To study synoptic charts, weather reports and symbols	

METEOROLOGICAL OBSERVATORY

Meteorological observatory is a place where all the necessary instruments are exposed for measuring weather phenomenon.

Four types of weather stations are recognized depending on the number of weather elements measured, the frequency of measurement and status of the observer. These four types of weather stations are Synoptic stations, Agricultural stations, Climatological stations and Rainfall stations. The surface observatories are divided into six classes and each class is coded with letter as follows:

Class A observatories: These are provided with eye reading instruments and self-recording instruments. the observations are recorded after every hour round the clock.

Class B observatories: Most of these are furnished with eye-reading instruments and self-recording instruments. Regular observations are made atleast twice in a day.

Class C observatories: These have the same instruments or equipment that are described in Class B observatories, but observatories are recorded only once in a day.

Class D, Class E and Class F observatories: These have a smaller number of instruments or equipment or are non- instrumental.

Agro-meteorological observatory

- Agro-meteorological observatory is a place where several instruments are installed and exposed to observe meteorological as well as biological parameters of crops.
- The observations are recorded at stipulated time. Agromet observatories are classified into three categories viz; i) Principal, ii) Ordinary and iii) Auxiliary types, depending upon the instruments (essential and optional) available in the observatory.
- The observations from Agro-meteorological observatories are recorded at stipulated time.
- These observatories are specifically located at the centre of the agricultural research farms of agricultural colleges and universities.

Principal Agro-meteorological observatory: The Central Agromet Observatory situated at Pune is one of such observatories. Principal Agromet Observatories undertake routine works, planned programmes and international collaborative projects.

Essential instruments

- | | |
|--|----------------------------------|
| 1. Maximum and minimum thermometers. | 8. Sunshine recorder. |
| 2. Wet and dry bulb thermometers. | 9. Assmann psychrometer. |
| 3. Soil thermometers. | 10. Dew gauge. |
| 4. Grass minimum thermometer. | 11. Thermo hygrograph. |
| 5. Rain gauge (ordinary and self-recording). | 12. Soil moisture equipment. |
| 6. Wind vane and anemometer. | 13. Solar radiation instruments. |
| 7. U.S.W.B. open pan evaporimeter. | |

Optional instruments

- | | |
|---|--------------------|
| 1. Lysimeter | 3. Potentiometer. |
| 2. Thermopile sensing elements for short and long wave net radiation. | 4. Microvoltmeter. |

Ordinary agrometeorological observatory: These stations record meteorological as well as biological observations on routine basis.

Essential instruments

- | | |
|--------------------------------------|--------------------------------|
| 1. Maximum and minimum thermometers. | 5. Rain gauge (ordinary). |
| 2. Wet and dry bulb thermometers. | 6. USWB open pan evaporimeter. |
| 3. Soil thermometers. | 7. Assmann Psychrometer. |
| 4. Grass minimum thermometer. | |

Optional instruments

- | | |
|-----------------------|-------------------------------|
| 1. Sunshine recorder. | 3. Self-recording rain gauge. |
| 2. Dew gauge. | 4. Thermo hygrograph. |

Auxiliary Agro-meteorological observatory: These types of observatories are equipped with few instruments and collect qualitative data on phenology and insects and diseases of economic importance to important crops of the region.

Essential instruments

- | | |
|--|-------------------------|
| 1. Maximum and minimum thermometers. | 3. Ordinary rain gauge. |
| 2. Dry bulb and wet bulb thermometers. | |

Optional instruments

- | | |
|------------------------------|---------------|
| 1. Wind vane and anemometer. | 2. Dew gauge. |
|------------------------------|---------------|

CRITERIA FOR SITE SELECTION

- The site should contain a flat rectangular plot with 55 meters (180 feet) in north-south direction and 36 meters (120 feet) in east-west direction
- The site must be representative of climate, soils and agricultural (cropping) conditions of the area and should be located at the centre of the farm,
- The site must be free from water logging and easily accessible throughout the year,
- Site selected should be away from hills, buildings, streams and trees to avoid shade, shield or channel affects,
- It should be away from steep slopes, water bodies and frequent irrigation.
- The recommendable distance from the obstacles from the rain gauge and other instruments are at least twice and 10 times the height of the obstructions, respectively.

Fencing:

After the site selection, it should be wire fenced, normally to a height of about 1.5 meter with a gate locking arrangement to protect from theft, animals and rodents which may cause damage to cables.

Surface conditions: The surface of the observatory should be cleaned regularly and be covered with thin grass as barren ground causes increased ground radiation. The grass should be periodically trimmed.

Selection of site for observatory: The following basic requirements should be met out in selecting site for establishment of observatory. Proper site selection will ensure that the observations are representative of the place and sufficiently comparable with those of other stations.

1. The site should be representative of the crop-soil-climate conditions of the area.
2. It should be located at the centre of the farm.
3. The site should be free from water logging.
4. It should have easy accessibility during the rainy season.
5. The site should be away from any permanent irrigation sources and tall structures like buildings, hillocks and trees.
6. The site should not have extreme topography and it should be well exposed and levelled.

Recommended layout


- The dimensions for an observatory are length of 55 m and width of 36 m and the longer side running South-North.
- The ground plan for an agromet observatory is given in Fig 1.
- The periphery should be fenced with barbed wires to prevent cattle trespass.
- There should be a gate at appropriate site.
- All tall instruments should be installed at the northern side of the observatory to avoid shade effect.

Time of observation

- The observations are recorded at 07.00 and 14.00 hours local mean time (LMT) all over India.
- However, rainfall and evaporation observations are taken at 08.30 hrs Indian Standard Time (IST) and 14.00 hrs LMT.
- The setting of automatic instruments like thermograph, hydrograph evaporigraph and barographs etc. are done at 08.30 hrs IST.

Major units in general use and measuring instruments

S. No.	Element	Unit	Instrument(s)
1.	Temperature	Degree Celsius (°C)	Thermometer, Hygrograph
2.	Wind speed	kmph, mps, knots	Anemometer, Anemograph
3.	Wind direction	Degrees clockwise from north on the scale 00-36, where 36 is the wind from the north, 09 from the east and 00 refers calm	Wind Vane, Anemograph
4.	Relative humidity	Per cent (%)	Dry and wet bulb thermometers, hygrograph
5.	Precipitation	millimeters (mm)	Rain gauge, dew gauge, snow gauge
6.	Evaporation	millimeters (mm)	Evaporimeters
7.	Duration of sunshine hours	hours (h)	Sunshine recorder
8.	Cloud cover	Oktas (1/8 of the celestial dome)	Visual, observed in the observatory
9.	Atmospheric Pressure	Inches or millimeters	Barometer



MEASUREMENT OF AIR TEMPERATURE

Temperature of the air is one of the important factors in crop - weather relations. Its measurement helps in understanding the rate and amount of water loss in the process of evaporation from the soil and transpiration from the plant system for a given environment. Temperature is measured using three type of scales namely Fahrenheit, Celsius and Kelvin. The melting point of ice on the three scales is 32°, 0° and 273° and boiling point of water is 212°, 100° and 373°, respectively. The relation between three scales are $^{\circ}\text{K} = ^{\circ}\text{C} + 273$; $^{\circ}\text{C} = 5/9(^{\circ}\text{F}-32)$ and $^{\circ}\text{F}=9/5(^{\circ}\text{C}+32)$

Temperature Instruments

1. **Maximum thermometer:** This is a mercury thermometer and records the highest or maximum temperature reached during past 24 hours or since last setting. Maximum temperature generally occurs in the world between 14.00 to 1600 hrs.
2. **Minimum thermometer:** This thermometer records the lowest temperature of air reached during last 24 hours or since last setting. Lowest temperature of the day generally occurs just before sunrise or clear day and after sun rise on cloudy day.
3. **Dry bulb thermometer:** This is a mercury thermometer which gives the prevailing temperature of air at 4' 3" to 4' 6" height. It is required to calculate relative humidity and vapour pressure.
4. **Wet bulb thermometer:** This is similar to dry bulb thermometer but the bulb of thermometer acts as an evaporating surface. It is used for calculating dew point, relative humidity and vapour pressure.
5. **Thermograph:** This instrument continuously records air temperature with passage of time. This is not an accurate instrument but its importance lies in its automatic recording of air temperature.
6. **Infra-red thermometer:** This is a sophisticated instrument used for measuring instant temperature. It contains thermocouple and thermistors upto accuracy 0.1 °C and response time less than one second. It is very accurate, rapid, and portable without any contact, temperature is obtained.

Maximum air temperature: The maximum temperature attained by air during the day is measured by a thermometer called maximum thermometer. It is a mercury-in-glass thermometer with a constriction in the bore below the lowest graduation. It allows the mercury to be forced through with rising temperature but prevent it being drawn back with falling temperatures, provided the thermometer is kept at an angle of 10° from the horizontal with the bulb downwards. It allows the mercury in one way as the constriction acts as a valve. The observer resets the thermometer after reading by holding it firmly in hand by the remote end from the bulb and swinging it briskly downwards. The range of maximum thermometer graduation is from -20°C to 55°C.

Minimum thermometer: The minimum temperature attained by air during the day is measured by using a thermometer called minimum thermometer. Minimum thermometer is an alcohol thermometer. Alcohol is sensitive for lower temperature than mercury. Within the liquid, there is a very light dumb bell-shaped glass index which moves freely within the spirit but not readily emerge from the liquid due to surface tension. The thermometer is tilted slightly so that bulb end is upward, the glass index slides along the tube until it reaches the meniscus. But when temperature rises, it remains stationary while the liquid moves ahead in the column. The range of minimum thermometer graduation is from -40°C to 50°C.

MEASUREMENT OF SOIL TEMPERATURE

Soil temperature in simple words is the measurement of the warmth in the soil. Soil temperature is an important factor for plant growth and development. Soil temperature affects the water movement within the soil and plays a vital role in germination of seeds and root system development. The activity of the soil micro-flora, decomposition of organic material and absorption capacity of roots depend on the soil temperature. An increase in soil temperature results in the increased solubility of some major salts.

Soil Thermometer: A soil thermometer is a mercury-in-glass thermometer. The bulb of this thermometer is bent at an angle of 120° while the stem is straight. The range of the thermometer is -20 to +60°C. The site for such measurements should be a level plot of size 180 cm X 120 cm in the observatory and typical of the surrounding soil for which information is required. The standard depths for measurement of soil temperature are 5, 10 and 20 below the surface. Additional depths may however be included. The thermometers are placed 45 cm apart at an inclined depth of 5.8, 11.6 and 23.2 cm to ensure a vertical depth of 5, 10, 15 and 20 cm respectively. In places where ground is covered with snow, it is desirable to measure the temperature of snow cover as well.

Installation

- Minimum soil layer should be disturbed during installation of thermometers inside the soil.
- The bulb of the thermometer should rest in good contact with the firm undisturbed soil.
- While digging the soil for installation, the soil should be removed layer wise and identically layers put in corresponding previous position.
- The zero mark of the thermometer should be at ground level.

Recording Observations: The soil temperature readings are taken read daily at 07.00 and 14.00 h LMT. The following points should be kept in mind while taking the observations:

- The line joining the observer's eye and top of the mercury column should be at right angle to the instrument.
- The observer should stand at some distance from the instrument so as not to shadow the ground surface in the vicinity of the instrument.
- Reading should be taken correct to 0.10°C.

Grass Minimum Thermometer: The grass minimum temperature is the lowest temperature reached overnight by a thermometer freely exposed to the sky just above short grass. The grass minimum temperature is measured with a minimum thermometer as described in

Section "Minimum Temperature Thermometer". The stem of this thermometer is however encased in a glass jacket in order to protect seal marks on the stem from dew, rain and prevent the stem from cooling rapidly. Grass minimum temperature indicates the chance of occurrence of ground frosts. A ground frost is likely to occur when the instrument records a temperature below 0°C.

Thermometers are mounted on suitable Y-shaped supports so that they are inclined at an angle of about 2° from the horizontal position, with the bulb being lower than the stem. The reading is taken before sunrise. After reading, the instrument is kept indoors to avoid direct exposure to solar radiation. The grass minimum temperature remains lower than the air temperature at screen level.

MEASUREMENT OF RAINFALL BY FRP RAINGAUGE, SELF-RECORDING RAINGAUGE

- Water in any form falling on the earth is called precipitation.
- The main forms of precipitation falling to the ground are drizzle, rain, snow and hail.
- Rain is the liquid form of precipitation, while snow and hails consist of solid ice crystals. Dew and frost are ground precipitation, which do not fall but form near and ground on the vegetation.
- Rain is an important form of precipitation and is the main source of soil moisture for crop production.

Instruments required

1. Ordinary rain gauge
2. Self-recordingrain gauge

Rainfall measurement

- The principle of rainfall measurement is to measure the depth of the layer of the water that has fallen.
- Five millimetre of rain means if that rainfall is collected on flat surface, the height of water would have been 5 mm.

Ordinary rain gauge

- This rain gauge consists of a funnel, provided with a rim, which is circular and exactly 127 mm in diameter. The rim of the rain gauge is 30 cm above the ground level and 25.4 cm above the cemented plat form.
- The rain water collected in receiver is measured with the help of a standard measuring cylinder provided with the instrument. The capacity of the receiver is 4 litres.
- A measuring cylinder calibrated in mm is used to measure the rainfall.
- The measurement is taken daily at 8.30 hrs IST and 14.00 hrs LMT as and when there is rain. The rainfall of last 24 hrs is recorded in the column of observation day.

Measurement of rainfall

- The rainwater from the receiver is carefully poured in to the measuring glass kept on the horizontal surface. The observer maintains his eye at the level of water in the measuring glass.
- Reading is noted from the lower meniscus avoiding parallax.

Care and maintenance

1. The funnel should not get choked with dirt.
2. The receiver should be always kept clean.
3. The measuring glass should be kept spotless clean.
4. All the parts should be examined regularly for choking and leakage.
5. While replacing the funnel, see that it is pressed down evenly from all sides.

Self-recording raingauge: This is a natural siphon type rain gauge used for measuring the amount, duration and rate of rainfall continuously. The instrument consists of three main parts **Funnel, Recordingmechanism and Receiver**

The receiver consists of float and siphoning chamber. Rain water enters the receiver through eight-inch diameter funnel. A pen is mounted on the stem of the float. As the level of water rises in the receiver, the float rises and the pen records continuously the amount of water in the receivers on a chart placed on a rotating drum with clockwork arrangement. The clockwork drum revolves once in 24 hrs or 7 days. Siphoning starts automatically when the pen reaches the maximum point of the chart. If the rain continues, the pen rises again from the zero line on the chart. If there is no rain, the pen traces the horizontal line from where the rain stopped.

Rainy day- If the rainfall of a day is 2.5 mm or more then it is called as a rainy day.

MEASUREMENT OF EVAPORATION

Observations to be Recorded: Evaporation is measured every day at 8:30 am IST. The observations to be recorded are:

1. Temperature of water in the pan.
2. Amount of water added or removed to bring back level to the tip of the pointer.
3. Amount of rainfall during the past 24h.

Evaporation measurement is done for in different conditions.

No Rainfall: When there is no rainfall, measured quantity of water is added to the evaporation pan up to the tip of the pointer using the measuring bucket. The evaporation is equal to the amount of water added to the pan.

Rainfall with Pointer Above the Water Level: When there is rainfall, but the tip of the fixed-point gauge remains above the water level, measured quantity of water is added by measuring bucket till the water level reaches tip of the pointer in the stilling well. Evaporation is estimated as:

$$\text{Evaporation} = \text{Water added} + \text{Rainfall during the period}$$


Rainfall with Pointer Below the Water Level: When rainfall is more than evaporation and the water level inside the stilling well is above the tip of the pointer, in this case water is removed from reservoir with the help of measuring bucket until the level of water comes to the tip of the pointer. Evaporation is estimated as:

$$\text{Evaporation} = \text{Rainfall during the period} - \text{Water removed}$$

Overflow: When there is heavy rainfall, over flow will take place from the pan, evaporation cannot be recorded.


MEASUREMENT OF EVAPOTRANSPIRATION

For determination of evapotranspiration, lysimeters are used. A lysimeter is a special water tight tank containing a block of soil and set in a field of growing plants. The plants grown in the lysimeter are the same as in the field. Evapotranspiration is estimated in terms of the amount of water required to maintain constant moisture conditions within the tank measured either volumetrically or gravimetrically through an arrangement made in the lysimeter. Lysimeters should be designed to accurately reproduce the soil conditions, moisture content, type and size of the vegetation of the surrounding area. They should be so buried that the soil is at the same level inside and outside the container. There are three types of lysimeters:



Non-weighing Type Lysimeters: Non-weighing (percolation-type) lysimeters can be used only for measuring volumetric changes in water balance weekly or biweekly. They do not provide accurate daily estimates. A simple non-weighing lysimeter is shown in Fig. Irrigation water is applied to the lysimeter. A layer of pebbles is placed at the bottom to facilitate easy drainage. Excess water is collected from below at a suitable distance.

Weighing Type Lysimeters: Weighing lysimeters provide precise information on soil moisture changes for daily or even hourly periods. This lysimeter is mainly composed of an inner tank, which is placed inside another tank. The outer tank is in contact with the surrounding soil. The inside container can be isolated from the outer tank and is weighed by scales. A heavy liquid like $ZnCl_2$ can be used to float the tank in water and the water gain or loss is estimated in terms of water displaced. This lysimeter is most commonly used for ET measurement but it has some important limitations. The restricted root growth, the disturbed soil structure in the lysimeter causing changes in water movement and possibly the tank temperature regime, resulting in condensation of water on the walls of the container. Harrold and Dreilbelbis (1967) estimated that errors due to dew formation were in the order of 250 mm per annum. Other limitations include the 'bouquet effect' whereby the canopy of the plants grown in the lysimeter is above and extends over the surrounding crop, resulting in a higher evapotranspiration rate. In spite of these limitations, it is the best technique for precise studies on evapotranspiration.




Floating Type Lysimeters: In this lysimeter, soil is placed in a hollow-walled tank that floats in water inside a slightly larger reservoir tank. A loss or gain of weight in the floating tank results in a change of water level in the reservoir tank and stilling well. This level is recorded by a sensitive water-level recorder. Any overflow from an excessive weight on the floating tank is retained in an overflow tank at the recorder.


MEASUREMENT OF SUNSHINE DURATION

For the measurement of sunshine duration, following instruments and accessories are required:

- i. Campbell-Stokes sunshine recorder.
- ii. Sunshine card.
- iii. A special plastic scale.



Campbell Stokes sunshine recorder: The Campbell-Stokes Sunshine Recorder consists of a 10 cm diameter glass sphere mounted on a spherical bowl. There are three partially overlapping grooves in the bowl in which three different types of cards are placed. The glass sphere is focused so that an image of the sun is formed on recording paper. Three different recording cards are used depending on the season.



Recording Cards: The cards are made up of a good quality pasteboard of 0.04 mm thickness and are blue in color. This color enables the card to absorb the radiation and gives a good contrast when burned. There are three different types of cards. The short curved are used for winter season, long curved card for summer season and straight cards in equinoxes are used.

Measurement of Sunshine Duration

Cards	Season	Period	Grooves
Short curved	Winter	15th October to end of February	Upper
Long curved	Summer	12th April to 2nd September	Lower
Straight	Equinoxes	3rd September to 14th October; 1st March to 11 th April	Middle

Special Plastic Scale: This is a type of time scale used to measure the length of burn to obtain the duration of sunshine. The scale is made up of celluloid and each hour is divided into 10 parts consisting of 0.1h or 6 min. The parallel sunshine scale is used for straight cards and trapezoidal scale is used for long and short curved cards.

Installation and Working: The instrument is installed on a masonry pillar of 10 ft. (3.04 m) above the ground. The sphere is supported on the bowl according to the latitude of the place where the observatory is located.

The focus of the sphere shifts as the sun moves, and a burn trace is left on the recording card at the focal point. A burn trace at a particular point indicates the presence of sunshine at that time, and the recording card is scaled with hour marks so that the exact time of sunshine occurrence can be ascertained. Measuring the overall length of burn traces reveals the sunshine duration for that day. The total length of the burn is measured with the help of the special plastic scale.

Procedure:

1. A suitable card depending on the season is set in the suitable groove.
2. Insert the card in the appropriate groove of the recorder such that the 12 h line coincides with the noon mark engraved on the bowl.
3. After sunset remove the burnt card.
4. Measure the burns using the special plastic scale.
5. Add up the values for all the hours and determine the total duration of sunshine hours for the day.

MEASUREMENT OF TOTAL SOLAR RADIATION

Global solar radiation can be measured by converting radiant energy into electro-magnetic force as in thermopiles. Total short-wave radiation or global radiation on a horizontal surface can be measured by Pyranometers.

Pyranometer: In the absence of the instrumentation for observing solar radiation, the solar radiation receiving on the surface of the earth could be estimated by using the relationship between the duration of sunshine and radiation (Table 1). That is, radiation (calories/cm²/day) is directly proportional to number of bright sunshine hours. Higher the sunshine hours, larger the radiations received and *vice versa*. This can be given in Angstroms formula as:

Q = QA (a+b n/N); Where Q = the radiation actually received on the surface of the earth (cal/cm²/day)

QA = Angstroms value (extra-terrestrial radiation value incident outside the earth's atmosphere)

n = actual number of sunshine hours in a day as observed

N = Maximum possible duration of sunshine (depends on the latitude of the place)

a & b = constants depending upon the locations(latitude sun angle)

Case I- when n=N that is actual sunshine equal to maximum possible sunshine under clear sky

$$Q = QA (a+b n/N) = QA (a+b)$$

Maximum radiation received on the earth surface.

Case II - n =0, due to continuous overcast conditions throughout the day

$$Q = QA (a+b 0/N) = QA(a)$$

Lowest radiation received due to scattering effect of clouds.

Q is not equal to 0, even if n=0. It is due to the fact that diffused radiation is received even on cloudy days.

MEASUREMENT OF WIND DIRECTION

The instrument used for the measurement of wind is wind vane. The direction from which wind blows is known as the windward side and towards which it blows is known as leeward side.

Wind vane: Wind vane consists of a brass-arm, mounted on ball bearing to a vertical axis. To one side of the brass arm there is an arrowhead and on another side there are two flat vanes forming an acute angle (about 20°). The ball bearings are in bearing house where there is an oil hole. The screw below the bearing are in bearing house are tightened to a brass covering known as brass sleeve. Below the wind vane there are 4 direction arms fixed to the vertical axis by means of a brass boss. In between the direction arms there are corner indicators. The direction arms and corner indicators are tightened to the brass boss by means of knots known as check knots. The direction arms are levelled with N, S, E and W. The vertical axis is erected by means of an iron-stand.



Units: Wind direction can be expressed in two ways:


1. By direction (Sixteen point of a compass).
2. By degree (from north, measured in clockwise as N, E, S, W means 360°, 90°, 180° and 270° respectively).

Observation: Watch the wind vane for a few minutes and identify the direction nearest to the sixteen point of the compass.

Wind direction

Measurement of Wind Speed: Wind speed is measured by means of an anemometer. There are two types of rotating anemometers: the cup anemometer, which has three or four cup wheels attached to the rotating axis, and the propeller anemometer, which has propeller blades. Both types rely on the principle that the revolution speed of the cup or propeller rotor is proportional to the wind speed.

Cup Anemometers: A cup anemometer has three or four cups mounted symmetrically around a free-wheeling vertical axis. The difference in the wind pressure between the concave side and the convex side of the cup causes it to turn in the direction from the convex side to the concave side of next cup. The revolution speed is proportional to the wind speed irrespective of wind direction. Wind speed signals are generated with either a generator or a pulse generator.



The cups were conventionally made of brass but in recent years, cups made of light alloy or carbon fiber thermo-plastic have become the common, allowing significant reductions in weight. Beads are set at the edges of the cups to add rigidity and deformation resistance. They also help the cup to avoid the effects of turbulence, allowing the stable measurement of a wide range of wind speeds.

The anemometer is installed on a metal pipe, which is fixed on a wooden post.

The height from the center of the anemometer cups is 10 ft. above the ground level.

Units: A number of different units are used to indicate wind speed. Some of the common units of measurement are

Conversion of units of wind speed	kt	m/s	km/h	mph	ft./s
	1	0.515	1.853	1.152	1.689

- i. meters per second (m/s),
- ii. kilometers per hour (km/h),
- iii. miles per hour (mph),
- iv. feet per second (ft./s) and
- v. knots (kt).

Wind Rose: Wind direction is normally defined by a wind rose. Wind rose is a graphic display of the distribution of wind direction at a location during a defined period. The characteristic patterns can be presented in either tabular or graphic forms. A wind rose is a set of wind statistics that describes the frequency, direction, force, and speed. In this plot the average wind direction is shown as one of the sixteen compass points, each separated by 22.5° measured from true north. The length of the bar for a direction indicates the percent of time the wind came from that direction. Since the direction is constantly changing, the time percentage for a compass point includes those times for wind direction at 11.25° on either side of the point. The percentage of time for a velocity is shown by the thickness of the direction bar.

Preparation of Wind Rose

- i. A circle is first divided into 8, 12, or 16 sectors representing the directions of wind flow.
- ii. The percentage of time the wind blows from each direction is determined from wind direction data. **Table** shows a sample frequency data table for preparation of wind rose.
- iii. The data is then plotted on a circular graph as a line emanating from the center of the circle. The length of the line is scaled to the percentage obtained from the data, pointing in the given direction.
- iv. The wind speed can be included in wind rose diagram. For this purpose, the percent of time that the wind is blowing at given speeds toward each direction needs to be determined. This data is then plotted as scaled blocks on the line showing wind direction.

Direction	Frequency	Percentage (%)
N	165	22
NE	65	14
E	142	5
SE	17	3
S	65	9
SW	59	11
W	38	9
NW	150	27
Total	701	100

INSTRUMENTS FOR MEASUREMENT OF RELATIVE HUMIDITY

Stationary or simple Psychrometer: It consists of two mercury thermometers with the bulbs of identical form and size. A set of these two thermometers (Dry and Wet bulb) is known as simple Psychrometer. Both are exposed vertically in Stevenson's screen. The dry bulb thermometer indicates the actual temperature at the time of observations and the wet bulb thermometer indicates the temperature of cooled air by converting the bulb to an evaporating surface. With the help of hygrometric table dew point temperature and relative humidity are obtained.

Assmann Psychrometer: Assmann devised this instrument in 1887 in Berlin. This instrument consists of a pair of dry and wet bulb thermometer with the cylindrical bulb forms, fixed vertically. Each bulb is protected from external radiation by two highly polished coaxial tubes. The instrument is designed for measuring the temperature and relative humidity both in the open as well as inside crops. In this psychrometer, the aspiration is provided by means of a clockwork fan by which air is drawn at a speed higher than 10 feet per second (fps).

Whirling Psychrometer: Anago devised this in 1830. This instrument is used to measure the temperature and relative humidity of the air in the open as well as inside crops at various heights. It consists of two thermometers attached horizontally to a rectangular wooden frame. Both the thermometers can be rotated with handle. This psychrometer should be given about 4 rotations per second to obtain desirable wind speed of about 5m per second. By the readings of dry and wet bulb thermometers of Assmann and Whirling psychrometer, dew point temperature, vapour pressure and relative humidity at different heights can be calculated. These two instruments are used to measure microclimatic observations in the laboratory near a microclimatic post. It is a wooden post of 3" X 3" X 12' size with markings at 1', 2', 4', 8' and 12' heights. It is painted white and by the side of the post is placed a wooden ladder of 8' height.

Hair Hygrometer: Hair hygrometer is used to record humidity at the time of observations. A human hair is used in this instrument. It is circular in size and indicates humidity directly. It is kept in the laboratory to observe humidity in room temperature.

Hair hygrograph: It is an instrument used for continuously recording the relative humidity of the air. Human hair has a property to increase the length with increase in humidity and decrease with decrease in humidity. Thus, the instrument consists of a bundle of cleaned and de-oiled human hair, tied at both the ends and kept tight in the middle by means of a hook attached to one arm of the lever and second arm of the lever is associated with pen arrangement which can make marking on graph paper attached on the clock driven revolving drum. The changes in length of the hair thus, cause a displacement of the hook, which is communicated by second arm of the lever to record the changes on the graph paper. The circular drum rotates once in 24 hrs or once in a week. This instrument is placed inside a Stevenson's screen in the observatory. Its operation is based on the property of de-oiled human hair to vary its length.

SYNOPTIC CHARTS AND WEATHER REPORTS

After collection of data with various devices, the data need to be transferred to an appropriate place for analysis. In this regard, it is proper to know a little about synoptic climatology. The term synoptic climatology is applied to investigations of regional weather and circulation types. It is also used to refer any climatological analysis which makes some reference to synoptic weather phenomena. This field is concerned with obtaining an insight into local or regional climates by examining the relationship of weather elements individually or collectively to atmospheric circulation processes. Synoptic climatology is defined as the description and analysis of the totality of weather at a single place or over a small area, in terms of the properties and motion of the atmosphere over and around the place or area. There are essentially two stages to a synoptic climatological study:

1. The determination of categories of atmospheric circulation type
2. The assessment of weather elements in relation to these categories.

Besides agricultural meteorological observatories, synoptic weather stations also record weather data such as rainfall, temperature, radiation, low level wind and evaporation etc. The surface observatories collect information on various weather elements and based on these, daily forecasts, warnings and weather reports are prepared by weather forecasting centres at Chennai, Nagpur, Mumbai, Delhi and Kolkata. The weather bulletins are being broadcast in regional languages through All India Radio and Television.

Synoptic report: Observed weather conditions are marked in brief coded form as a synopsis of the conditions. Such a brief report on weather conditions is known as synoptic report.

Synoptic Chart: A synoptic chart is a map which summarizes atmospheric conditions (temperature, precipitation, wind speed and direction, atmospheric pressure and cloud cover) over a wide area at particular time locations. Synoptic charts are used for observation of movement of weather formations and prediction their future behavior and movements. Charts are

Symbol	Precipitation	Symbol	Cloud cover	Symbol	Wind speed
	Drizzle		Clear sky		Calm
	Showers		One oktas		1-2 knots
	Rain		Two oktas		5 knots
	Snow		Three oktas		10 knots
	Hail		Four oktas		15 knots
	Thunderstorm		Five oktas		20 knots
	Heavy rain		Six oktas		50 knots or more
	Sleet		Seven oktas		
	Snow shower		Eight oktas		
	Mist		Sky obscured		
	Fog				

updated at least every 6 h, and this allows meteorologists to make more accurate predictions. The symbols used for the preparation of synoptic charts are given.

SYNOPTIC WEATHER SYSTEMS IN INDIA

The climate of India consists of four seasons, two major seasons and two transitional seasons:

- South-west Monsoon (June–September),
- Transition-I, post-monsoon season (October–November),
- Winter season (December–February),
- Transition-II, Pre-monsoon season (March–May).

South-west Monsoon: The south-west summer monsoons (popularly known as monsoon) occur from June to September. It sets in over Kerala and then advances from south to north and from east to west. Normal onset date is 1st June. The south-west monsoon is generally expected to begin around the start of June and fade down by the end of September. Nearly 75% of the annual rainfall in India is due to south-west monsoon. Apart from south-eastern part of the Indian peninsula and Jammu and Kashmir, south-west monsoon is the principal source of rain in India. The monsoon accounts for 80% of the rainfall in India. Indian agriculture is heavily dependent on the rains, for growing crops especially like cotton, rice, oilseeds and coarse grains.

Post-monsoon season or North east monsoon season: Major weather disturbances in this season includes NE monsoon, cyclonic storms over Indian seas and low-level easterly waves at southern latitudes. The NE monsoon causes rainfall over peninsular India and parts of Sri Lanka. Cities, which get less rain from the South-west Monsoon. About 50–60% of the rain received by the state of Tamil Nadu is from the Northeast Monsoon. In Southern Asia, the northeastern monsoons take place from December to early March.

Winter season: Major Semi permanent synoptic feature is the sub-tropical westerly jet stream and the subtropical ridge. Both of them are seen over Indian longitudes. Major Synoptic weather systems in this season are Western disturbance, mid and upper tropospheric westerly waves at the northern latitudes and sometimes easterly waves at southern latitudes. During winter months, the Western Himalayas and adjoining northern parts of India experience cloudiness and rainfall/snowfall in association with weather systems commonly known as "Western Disturbances". These are responsible for heavy rainfall and snowfall in the Himalayas and Jammu and Kashmir.

Pre-monsoon Season: There is very little rainfall in India in this season. Some thunderstorms occur mainly in Kerala, west Bengal and Assam. Some cyclonic activity also occurs on the East Coast.

The routine duties of the observer include:

1. To make regular and careful observations and to note the general character of the weather and record in the pocket register.
2. To prepare and dispatch the weather telegram as per instructions to different forecasting centers, immediately after taking observations.
3. To send, heavy rainfall telegrams to the various offices on warning list.
4. To prepare and post monthly meteorological and pocket registers, for each month to the controlling meteorological office.
5. To keep the instruments clean and maintain them properly.

After sending the data by the observer, it should be decoded and the weather observations for each station must be plotted at the appropriate location in a systematic manner following the international station model. Only weather maps in first-class forecasting centers approach the completeness of the model. Printed maps and maps used for plotting usually have an appropriately numbered circle corresponding to each reporting land station and observations are plotted about this location in the appropriate position regardless of the number of observations shown. It must be, emphasized again that the weather pattern affecting a locality is an integral part of the much larger hemispheric weather pattern. It is necessary to plot a map over a large area. Even if observations are not to be plotted, it is necessary to know the plotting scheme in order to read and interpret weather charts already plotted.